



# Technical Bulletin 262


Version 1.0 29/01/2024

## Panther Firmware Update V1.47

This technical bulletin provides awareness of a firmware update relating to Panther and Panther PRO.

### Details of the firmware update:

- Colour has been added to the Panther PRO main screen Start/Stop Log buttons to make it clearer when the instrument is datalogging (see images below).



- An update has been made to the relative zero functionality. Users are reminded to ensure the instrument has cleared down before zeroing in a clean air environment. Calibration values will relatively track the set zero value when the instrument is zeroed. Users are recommended to wait approximately 30 seconds before zeroing on start-up.
- The update includes non-safety critical bug fixes for improved stability.

Please install the new firmware to ensure you are up to date.

### Who will the firmware update affect:

The update affects Panther and Panther PRO customers.

E: [info@ionscience.com](mailto:info@ionscience.com)

T: +44 (0)1763 208 503

Pioneering Gas Sensing Technology.  
[ionscience.com](http://ionscience.com)



### How can I access the update?

**Distributors, Customers and End Users** – If ION PC is already installed, please run ION PC, and await the automated prompt to download the latest firmware.

If you need to install ION PC, visit the [ION Science website](#).

Internal reference: P907-596

E: [info@ionscience.com](mailto:info@ionscience.com)

T: +44 (0)1763 208 503

Pioneering Gas Sensing Technology.  
[ionscience.com](http://ionscience.com)